




Cynex Copier MT5

Copy MT5 trades across accounts. Configure each receiver from the chart.

Send. Receive. Stay in control.

Cynex Copier MT5 copies trades between MetaTrader 5 terminals on the same Windows computer or Windows VPS. Send one account to several receivers, follow several sources in one account, or send and receive at the same time. Each receiver controls its own volume, symbol mapping and trade management.

Configure 68 operating settings directly in the chart dashboard. Overview, Connections, Copy settings, Trades, Activity and Help keep everyday work in one place.



Choose your connection pattern

- One MT5 source to one receiver or several receivers.
- Several named sources to one receiver, with source-specific settings.
- Two-way and many-to-many connections on the same machine.
- Copy manual and EA trades. Copied trades are excluded from outgoing updates to prevent copy loops.
- No separate connector, DLL or external subscription is required.

Set the volume for each receiver

- Seven lot methods: Same lots, Fixed lots, Multiplier, Balance ratio, Equity ratio, Stop loss risk and Lots per capital.
- Lot multiplier, additional lots and optional minimum and maximum volume.
- Explicit currency conversion for balance and equity ratios when account currencies differ.
- Per-source profiles or shared default settings.
- Broker volume steps and minimums are checked before execution.

Copy and manage the trade lifecycle

- Market positions and pending orders, including limit, stop and stop-limit orders.
- Source closure, pending cancellation, proportional partial closes and stop/target changes.
- Exact symbol aliases, receiver prefixes and suffixes, and optional symbol and magic-number filters.
- Optional direction reversal, market-to-pending conversion, opening delay and entry filters.
- Custom stops and targets, break-even, trailing stops and configurable account limits.
- Pause new copies, close a selected copy, or keep it locally for independent management.

Designed for clear recovery

The copier saves trade identities and execution intent, then reconciles them with orders, positions and history. A missing, expired or incomplete source update retains existing copies. Activity and in-panel Help explain connection and execution status.

Hedging and netting accounts are supported. On netting accounts, source contributions share a broker position. Per-contribution stops, targets, break-even and trailing are virtual and require the EA, terminal and broker connection to remain running.

Setup and operating requirements

- Install on every participating MT5 terminal under the same Windows user profile and Common Files location.
- Give each sending account a unique name. Enter those names in the receiver's Receive from field, separated by semicolons.
- Check symbols, contract sizes and volume settings. Save, confirm the connection, then enable copying on the receiver.
- Keep MT5 connected. Receiving requires the platform and EA Algo Trading permissions. Test your intended broker setup on demo first.
- This edition connects local MT5 terminals. It does not copy between separate computers over the internet, MT4 terminals or separate MetaQuotes virtual-hosting instances.
- Broker trading hours, permissions, margin, instrument specifications and execution rules apply. Fill prices and trading results can differ between accounts.

Contact me after your purchase to claim your complete package

After your purchase, send me a private message on MQL5 to receive your PDF user guide, access to the online course and MQL5 channel, setup assistance, and Smart Universal Expert Advisor FREE as your gift.

Your purchase includes

The MT5 utility, PDF guide, online course, MQL5 channel access and setup assistance. Message Issam on MQL5 to arrange your free Smart Universal Expert Advisor gift. The gift is optional and no review is required.

CYNEX / COPIER MT5

Start small. Check every step.

Install, connect, configure, then complete a small-volume demo test.

01 INSTALL

One chart per participating MT5 account.

02 CONNECT

Use unique sending names and matching receiver names.

03 CONFIGURE

Check symbols, volume and permissions.

04 VERIFY

Demo-test open, change, partial close and full close.

ISSAM ALGO

PDF guide, in-panel Help and setup resources | Contact Issam through MQL5

12 / 12

The separate user guide contains the full 68-setting dashboard reference and the demo acceptance sequence.